ATP Configuration Process

To configure ATP users should browse to the following URL: https://10.0.90.50 from the SEPM system.


ATP UI Login: User: Admin Pass: Symc4now!

ATP needs to be configured to connect to the SEPM. ATP has only been bootstrapped at this point.

Note* ATP may not have been started when the lab was deployed. If you are not able to see the login screen – make sure the ATP system is started via the https://labs.symantec.com interface.

RDP to the SEPM system and Configure ATP:

- 1. Log into ATP (https://10.0.90.50)
- 2. Goto Global Settings
- 3. Browse to the Synapse Section:
- 4. Select "Download Synapse Log Collector for SEPM Embedded DB"
- 5. Run install as **Admin** while logged into the SEPM system
 - a. Launch "cmd-as-admin" from the desktop
 - b. Type: cd "c:\users\testuser.CLOUD\downloads"
 - c. Type: SEPMLogCollector.msi
 - d. Provide the log collector configuration information:
 - e. Service IP Address: 10.0.10.20
 - f. Service Port: 8081
 - g. Log Collector Connection Password: <SET PASSWORD>
 - h. SEPM Embedded Password: P@ssw0rd9!




- 6. Select "Enable Symantec Endpoint Protection Correlation"
- 7. Select Add SEPM and configure with the following settings:


a. DB Type: Embedded DBb. Entry Name: SEPMc. IP Address: 10.0.10.20

d. Port 8081


e. Password: <USE ABOVE PASSWORD>



- 8. Download the SEPM SSL Cert from https://127.0.0.1:8443
- 9. In the EDR section:
 - a. Select Configure SEPM Controller
 - b. Entry Name: SEPMc. IP Address: 10.0.10.20d. Web Service Port: 8446e. User Name: Admin
 - f. Password: \$ymP@ssw0rd9!
 - g. Select "Add SEPM SSL Certificate" and browse the file downloaded from above.



10. Enable "Apply private cloud polices to all non-default SEPM groups"



- 11. Configure the rest of the EDR settings as needed.
- 12. Log into Victim1 and test by opening the Space-Science shortcut on the desktop and browse the page.